



ISO Image in Wavelab 6

An ISO image is a file that holds the entire contents of a data CD or DVD (files and folders). You can create an ISO image of a CD/DVD and burn it later in Wavelab.

1. In order to create an ISO image you must have a data CD/DVD project. This type of project can be created in Wavelab by clicking on the File menu, selecting New, and then choosing Data CD/DVD.



2. Once the Data CD/DVD project opens you will be able to navigate your computer and add items to the project that will be burnt to CD or DVD.
3. You may choose to save the Data CD/DVD to be burnt at a later time or to have as a back up. To do so, click on the CD (DVD) menu and choose save as ISO image.



4. Once this selection is chosen a dialog appears that allows you to name the ISO image and then another dialog follows that allows you to select the location within your computer of where you would like to place the ISO image.

5. In order to burn a CD/DVD from the ISO image at a later time click on the Tools menu within Wavelab and select Burn data-CD from ISO image.

