

## View Settings Files in Wavelab

View settings files (extension “.mem”) can store/recall information relating to a specific audio file such as window/zoom/scroll positions, Master Section preset etc. By default these files are stored in the same folder as the audio file they are associated with. Changing the destination for these files to a different folder on a different drive may increase the performance but also keeps the folder the audio file is in less cluttered with non audio files.

This folder can be specified from the Folders dialog; either directly or via the Preferences–Wave edit tab. Select Preferences from the Options menu and select the Wave edit tab.

- If the “Save view settings in companion file” option is activated, view memory files will be saved in the same folder as the related audio file.
- If you select “Save in independent folder” you can click the “Edit” button, which will open the Folder dialog with the “Peak and view memories” work folder selected. From here you can navigate to a new folder location to store the peak and view memory temp files.

### Saving a Master Section preset with an audio file

You can also store all Master Section settings used as part of the saved file. When you reload the file, you can choose to recreate the Master Section effects exactly as they were when saved. To store Master Section effects as part of an audio file, proceed as follows:

1. Make sure the effects and their settings are configured the way you wish to store them. “Save view settings in companion file” must be activated in the Preferences.
2. Select the file you wish to save a Master Section preset for, and [Ctrl]-click on the “M” button on the title bar. The button will now be lit up in green, to indicate that the Master Section effects settings have been saved.



3. Anytime you reload the file, you can recreate the Master Section effects by clicking on the “M” button. The effects will be loaded exactly as saved.